

# Messages and Codes

This chapter contains messages and codes issued by the HTTP server components of the SMARTS system.

The explanation of the messages is organized as follows:

- SMARTS HTTP ABEND Codes
- HTTP Server Messages (APSHTTP Prefix)

## Message Format

SMARTS HTTP server messages have the following format:

**APSHTPnnnn - message-id**

—where

HTP	identifies the HTTP subsystem as issuing the message.
nnnn	is a sequential message number identifying the message within the subsystem.
message-id	identifies the SMARTS address space issuing the message. This value is determined from the SMARTS server environment configuration parameter MESSAGE-ID. It may be a single character in braces (e.g. (X)) or it may contain the installation ID as specified in the SMARTS server environment configuration parameter INSTALLATION. Refer to the <i>SMARTS Installation and Operations Manual</i> for more information.

## Message Documentation

Messages are documented with the message identifier (excluding the constant ‘APS’ which is always present) in the heading followed by the message text.

The message text appears something like the following:

**This is a test &1 with three (&2) replacement parms '&3'**

When displayed or written to the console, the message contains the text as displayed; however, the placeholders identified by the ‘&n’ construct are replaced by data relevant to the message.

If the data to be displayed is X, y, and AB, the message appears as follows:

**This is a test X with three (y) replacement parms 'AB'**

Each message includes the following subsections:

Description	explains why the message was issued.
Placeholders	describes what each of the placeholders (that is, the '&n' values) contains. If the message contains no placeholders, the expression 'Not applicable' is written.
Action	describes the actions to be taken when this message is issued. A number of actions may be listed, if appropriate. If no action is required, the expression 'Not applicable' is written.
Additional References	describes any other additional source(s) of information that may further explain the message. A number of references may be listed, if appropriate. If no additional references are available, the expression 'Not applicable' is written.

## SMARTS HTTP ABEND Codes

### Overview of Messages

ABEND U2000 | ABEND U2001 | ABEND U2002 | ABEND U2003

#### ABEND U2000

#### Insufficient Storage

##### Explanation

ABEND U2000 occurs when insufficient storage is available to obtain a primary control block within the SMARTS HTTP environment. It indicates a problem at a point where it is not possible to issue a SMARTS HTTP error message.

##### Action

Make sufficient storage available to the program running in the environment to enable the request to be satisfied.

#### ABEND U2001

#### Logic Error in SMARTS HTTP Nucleus

##### Explanation

ABEND U2001 indicates an unexpected condition within the nucleus for which a message could not be issued.

##### Action

It could occur due to storage overwrites in the SMARTS HTTP environment or as a result of earlier errors in the environment. If none of these appears to be the case, report the problem to your local support center.

#### ABEND U2002

#### Invalid SMARTS local storage stack area

##### Explanation

On freeing the SMARTS HTTP server request's local storage stack area, it was found to be corrupt.

##### Action

See below for storage corruption explanation.

## ABEND U2003      Storage Corrupted

**Explanation** While freeing storage within the SMARTS nucleus, a corruption failure was detected.

**Action** When storage is allocated, SMARTS puts a storage accounting prefix at the start of the storage and an identical suffix at the end of the storage. If these do not match when the storage is freed, this ABEND occurs.

A mismatch indicates that either

- the user that allocated the storage requested "n" bytes but used more than "n" bytes thus overwriting the storage accounting area at the end; or
- a user of storage before the storage area being freed overwrote the prefix of the storage area.

In any event, register 7 will point to the prefix accounting area of the storage. The length of the storage is found at register 7 + 4 (if it hasn't been corrupted) while the storage area itself returned to the user can be found at register 7 + 8.

# HTTP Server Messages (APSHTP Prefix)

## Overview of Messages

HTP0001 | HTP0002 | HTP0003 | HTP0004 | HTP0005 | HTP0006 | HTP0007 | HTP0008 | HTP0009 |  
HTP0010 | HTP0011 | HTP0012 | HTP0013 | HTP0014 | HTP0015 | HTP0016 | HTP0017 | HTP0018 |  
HTP0020 | HTP0021 | HTP0022 | HTP0023 | HTP0024 | HTP0026 | HTP0027 | HTP0028 | HTP0030 |  
HTP0031 | HTP0032 | HTP0033 | HTP0034 | HTP0035 | HTP0036 | HTP0037 | HTP0039 | HTP0040 |  
HTP0041 | HTP0042 | HTP0043 | HTP0044 | HTP0047 | HTP0048 | HTP0054 | HTP0055 | HTP0056 |  
HTP0057

---

### HTP0001      HTTP server already active

**Explanation** An attempt was made to issue an INIT command to an HTTP server; however, the HTTP server was already active.

**Placeholder** Not applicable

**Action** Not applicable

**References** Not applicable

### HTP0002      Insufficient storage for \$2 (\$1 bytes)

**Explanation** An attempt by the HTTP server to acquire storage failed due to insufficient storage either in a user program thread or in the SMARTS address space.

**Placeholders**

\$1	Number of bytes that the system tried to acquire. The number may be suffixed with a 'K' or an 'M' to denote KBYTES or MBYTES, respectively. '0' indicates that the HTTP server was not in a position to determine the amount of storage that could not be acquired. This could occur if a request to an underlying system failed due to a storage shortage without indicating how much was required.
\$2	A character string indicating what the storage was for and possibly a four-digit code in braces indicating which control block this storage was for, if applicable.

**Action**

- If the storage is thread-related, use the ULIB utility to increase the catalog size of the HTTP server application program that suffered the error. Note that the thread sizes in general may have to be increased in the SMARTS region depending on how much thread space the application requires.
- If the storage is outside of the thread, there is a shortage of storage in the SMARTS region itself. Where possible, SMARTS will expand its storage areas so it is likely that such an expansion request failed thus resulting in this message. Check for other errors related to any attempted expansion for more details.
- The following table identifies the storage areas by name, where they may be located and what they are used for:

Storage name	Location	Description
Master control block (HMCB)	Above	The main control block used by the HTTP server; acquired from the SMARTS environment general buffer pool.
Working storage	Above	The generic term used for storage acquired on a temporary basis. It will normally be allocated in the HTTP server application program thread.
HTTP request areas (HPRQ and buffers)	Above	The main HTTP server request processing block and associated buffers acquired by the HTTP server request processing program HAANRQST from the application program thread.
HTTP request header (HPRH)	Above	The request header control block acquired per request header found in any given HTTP request. It is allocated from the HTTP server request processing program (HAANRQST) thread.
HTTP environment variable work area	Above	Area allocated from the HTTP server request program thread storage to issue 'putenv' requests to the SMARTS environment to build environment variables for CGI requests.

**HTP0003 Invalid parameter specified \$1**

**Explanation** An invalid parameter was specified on the HTTP server startup. This may have been supplied on the SMARTS server environment SERVER configuration parameter or operator command.

<b>Placeholders</b>	<table border="1"> <tr> <td>\$1</td><td>The string presented as a parameter to the HTTP server, which was not recognized.</td></tr> </table>	\$1	The string presented as a parameter to the HTTP server, which was not recognized.
\$1	The string presented as a parameter to the HTTP server, which was not recognized.		

**Action**

- Correct the SMARTS server environment configuration parameter SERVER to start the HTTP server.
- Reissue the SMARTS server environment operator command SERVER INIT with a valid parameter value.

**References** SMARTS Installation and Operations Manual

**HTP0004 Server initialization failed**

**Explanation** An attempt to start an HTTP server failed. The reason for the failure is indicated in a previously issued message.

**Placeholders** Not applicable

**Action** Correct the problem that caused the HTTP initialization failure as specified in the preceding message.

**References** Not applicable

**HTP0005 URL parameter data exceeds maximum (\$1 Bytes)**

**Explanation** A user issued an HTTP request with a parameter on the URL that exceeded the length of the URL parameter area. The URL parameter is the data following the question mark, which in turn follows the actual URL itself. The URL parameter buffer is allocated based on the HTTP server configuration parameter URLPBUFL.

<b>Placeholders</b>	<table border="1"> <tr> <td>\$1</td><td>The maximum URL parameter length of data in bytes that is acceptable to the instance of the HTTP server on which the error occurred.</td></tr> </table>	\$1	The maximum URL parameter length of data in bytes that is acceptable to the instance of the HTTP server on which the error occurred.
\$1	The maximum URL parameter length of data in bytes that is acceptable to the instance of the HTTP server on which the error occurred.		

**Action** Determine if the request itself is valid and if so, increase the specification of the HTTP server configuration parameter URLPBUFL accordingly.

**References** The chapter HTTP Server Use and Customization starting on page in this manual.

**HTP0006      Content length exceeds maximum (\$1 Bytes)**

**Explanation**      A user issued an HTTP request with content that exceeded the length of the allocated content area. The content of an HTTP request is the data that follows the last HTTP header provided for a request. The content buffer is allocated based on the specification of the HTTP server configuration parameter CONTBUFL.

**Placeholders**

\$1	The maximum length of content data in bytes which is acceptable to the instance of the HTTP server on which the error occurred.
-----	---

**Action**              Determine if the request itself is valid and, if so, increase the specification of the HTTP server configuration parameter CONTBUFL accordingly.

**References**        The chapter HTTP Server Use and Customization starting on page in this manual.

**HTP0007      Content length required for request**

**Explanation**        Where content is provided for an HTTP request, a 'CONTENT-LENGTH' header must be provided on the request to determine how much content to expect. This message is issued when the last HTTP header is received that is followed by content data; however, no content length header has been received.

**Placeholders**      Not applicable

**Action**              Determine which client is submitting the HTTP request and change it to either submit no content data or to submit a content length header indicating how much content data will follow.

**References**        The HTTP V1/1 Protocol specification

**HTP0008      Server is not active**

**Explanation**        An operator command has been issued to an HTTP server or an attempt has been made to terminate an HTTP server that is not active.

**Placeholders**      Not applicable

**Action**              Not applicable

**References**        Not applicable

**HTP0009      Content length ‘\$1’ invalid for request**

**Explanation** Content data has been provided on a HTTP request. Content data has been detected and a content length header has been provided; however, the content data provided was less than or greater than the length specified in the content length header.

<b>Placeholders</b>	\$1	The length of data expected based on the length provided in the content length HTTP header.
---------------------	-----	---

**Action** Determine which client issued the HTTP request and correct its content length processing.

**References** The HTTP V1/1 Protocol specification

**HTP0010      URL ‘\$1’ not found**

**Explanation** A client requested that the URL indicated in placeholder \$1 be returned; however, the URL does not exist.

<b>Placeholders</b>	\$1	The URL as requested by the client program.
---------------------	-----	---

**Action** This generally occurs for a dataset or dataset and member request. The HTTP server translates a URL of the form /a/b/c/ to a sequential dataset name of the form a.b.c , or a URL of the form /x/y/z to a PDS member name of the form x.y(z). The sequential dataset or PDS member as translated from the URL by the HTTP server was not found on the system. This indicates that either it doesn't exist or it has not been cataloged.

**References** Not applicable

**HTP0011      Unable to load CGI program ‘\$1’**

**Explanation** A request was issued that resulted in the URL being interpreted as a CGI request for the program identified by placeholder \$1. This program was not available to the SMARTS address space and therefore the CGI request could not be completed.

<b>Placeholders</b>	\$1	Name of the program identified by the CGI request which could not be loaded in the SMARTS region where the request was received.
---------------------	-----	--

**Action** Determine if the request was valid and if it was, make the program available in the SMARTS region where the request should be processed.

**References** The chapter Running CGI Programs under SMARTS starting on page in this manual.

**HTP0012      Natural startup module ‘\$1’ not found: ‘\$2’ NATCGI request failed**

**Explanation**    A request was received by the HTTP server that resulted in an attempt to execute the Natural CGI program identified by the \$2 placeholder. It was not possible to process this request as the Natural thread-resident portion identified by the \$1 placeholder could not be loaded in the SMARTS region where the request was received.

**Placeholders**

\$1	Name of the thread-resident Natural portion that is identified on the HTTP server configuration parameter NATTHRD.
\$2	Name of the Natural program that the Natural CGI request was attempting to execute.

**Action**            Correct the specification of the HTTP configuration parameter NATTHRD to identify the correct Natural thread portion; or make the Natural thread portion named available to the SMARTS region where the request was received.

**References**        The chapter Installing Natural CGI starting on page in this manual.

**HTP0013      Module \$1 loaded**

**Explanation**    The module identified by the \$1 placeholder was loaded by the nucleus. This message is issued in the following cases:

- When more than one version of a module exists, it indicates which version of the module was loaded.
- For exits that may not normally be part of the nucleus, this indicates when an exit has been loaded and is active in the system.

**Placeholders**

\$1	Name of the module that was loaded.
-----	-------------------------------------

**Action**            This is an informational message, no action is necessary.

**References**        Not applicable

**HTP0014      Server initialization in progress**

**Explanation**    The HTTP server has commenced its initialization processing.

**Placeholders**    Not applicable

**Action**            Not applicable

**References**        Not applicable



**HTP0015      Read error ‘\$1’ processing URL ‘\$2’**

**Explanation**    A URL identifying a sequential dataset or PDS member has been received. This dataset or PDS member has been found; however, an error occurred while reading the data to transmit it to the user.

<b>Placeholders</b>	<div>\$1</div> <p>The error number returned by the SMARTS API function being used to read the dataset or PDS member. Refer to the <i>SMARTS SDK Programmer's Reference Manual</i> for a cross reference of error numbers to C macro variable names identifying the error that has occurred. The HTTP server uses the ‘gets’ and ‘read’ functions to access data, so refer to the descriptions of these functions for details of the cause of the identified error number being returned.</p>
	<div>\$2</div> <p>The URL as requested by the user.</p>

**Action**            Use the returned information to identify the problem and correct it.

**References**       SMARTS SDK Programmer's Guide SMARTS SDK Programmer's Reference Manual

**HTP0016      ‘putenv’ failed processing environment variables errno=\$1**

**Explanation**    When a CGI request is identified, the HTTP server must make a number of specific environment variables available to the CGI program. This is done by using the SMARTS API ‘putenv’ function to set the environment variables before calling the CGI program. This indicates that the function request failed and therefore one or more environment variables will not be available to the CGI program called.

<b>Placeholders</b>	<div>\$1</div> <p>The error number as returned by the ‘putenv’ function. Refer to the <i>SMARTS SDK Programmer's Reference Manual</i> for details of errors returned by the ‘putenv’ function.</p>
---------------------	--

**Action**            Based on the information returned, determine why the ‘putenv’ function failed and correct the problem. Normally, ‘putenv’ only fails when insufficient storage is available in the thread where the CGI program runs. This is determined by the size at which the HTTP server request processing module (default name HAANRQST) is catalogued using the ULIB utility.

**References**       SMARTS SDK Programmer's Reference Manual

**HTP0017      \$1 Sockets \$2 request error errno=\$3**

**Explanation**    The HTTP server uses the SMARTS API sockets functions to communicate with clients. This message indicates that the request indicated by the \$1 placeholder failed with the error number indicated.

<b>Placeholders</b>	\$1	Name of the sockets function request that failed
	\$2	Error number
	\$3	Error number

**Action**            Sockets errors generally occur when the peer program terminates the conversation, or a transport error occurs on the network.

**References**        SMARTS SDK Programmer's Reference Manual

**HTP0018      Access to URL '\$1' forbidden**

**Explanation**    A user attempted to access the URL identified by \$1 but access to the resource was denied. This occurs depending on the specification of the HTTP server configuration parameter LOGON as follows:

- When LOGON=REQUIRED is specified, or LOGON=ALLOWED is specified and the user supplies authorization information (user ID and password) for the request, this error indicates that access to the resource based on the provided information was not granted.
- When LOGON=DISALLOWED is specified and the 'public' user ID does not have access to the requested resource, the user is not permitted to provide authorization information so the request is refused.

<b>Placeholders</b>	\$1	The URL that the user attempted to access.
---------------------	-----	--

**Action**            If the resource should be accessible to users of the HTTP server in question, grant the necessary access rights. If not, determine why users are attempting to access the resource in question.

**References**        The information on Security.

**HTP0020 Internal logic error in \$1+x\$2**

**Explanation** Something unexpected has occurred in the HTTP server nucleus. Additional errors are likely to follow any occurrence of this error message.

<b>Placeholders</b>	\$1	Name of the HTTP server nucleus program in which the error was detected.
	\$2	Hexadecimal offset in the program where the error was detected.

**Action** Report the error message and the steps taken to produce the error to your local support center.

**References** Not applicable

**HTP0021 Server is quiescing**

**Explanation** The HTTP server is quiescing. In this state, current requests may continue to completion; however, no new requests are allowed.

**Placeholders** Not applicable

**Action** This is an informational message: no action is necessary.

**References** Not applicable

**HTP0022 SAF Logon for default userid \$1 failed**

**Explanation** The default user ID specified is not authorized.

<b>Placeholders</b>	\$1	Default user ID
---------------------	-----	-----------------

**Action** Check that the default user ID specified in the HMANCONF macro by the parameter HTTPUSER is valid.

**References** The information on Security

**HTP0023 Invalid URL '\$1'**

**Explanation** The URL requested by a client is invalid.

<b>Placeholders</b>	\$1	The URL as requested by the client
---------------------	-----	------------------------------------

**Action** Specify a URL that the HTTP Server can understand. Refer to the appropriate IETF standards for information on what constitutes a valid URL.

**References** Not applicable

**HTP0024      Natural initialization failure, RC=\$1**

**Explanation** A request was received by the HTTP server that resulted in an attempt to execute a Natural CGI program. The Natural thread-resident portion that is identified on the HTTP server configuration parameter NATTRD was loaded, but an error occurred at startup.

<b>Placeholders</b>	\$1    The return code received from the Natural thread-resident portion.
---------------------	---

**Action** Determine from the Natural documentation why the return code is returned and correct the error.

**References** Natural Installation and Operations Manual.

**HTP0026      Conversation \$1 no longer exists**

**Explanation** When a conversation is started with a WWW browser, it is assigned an internal identifier known only to the HTTP server and the browser with which it is conversing. This error indicates that when the browser eventually sent data in response to a request, the original conversation no longer existed. This could occur due to a timeout, a system ABEND, or even a stored URL being sent minutes, hours, days, or even weeks after the conversation was terminated normally by the user.

<b>Placeholders</b>	\$1    Name of the conversational cookie.
---------------------	---

**Action** Restart the conversational application as appropriate.

**References** Not applicable

**HTP0027      Input buffer space \$1 bytes exhausted**

**Explanation** This error occurs if pooled sessions are in use and the entire request from the user must fit into the input buffer. The message is longer than the input buffer length specified in the configuration for the HTTP server.

<b>Placeholders</b>	\$1    The length of the buffer used for receiving input data from the network.
---------------------	---

**Action** Increase the specification of the HTTP server configuration parameter RECVBUFL.

**References** The chapter HTTP Server Use and Customization starting on page in this manual.

**HTP0028      Server interface \$1 request failed rc=\$2**

**Explanation**    A call to the environment independent server interface failed.

<b>Placeholders</b>	\$1	The server function requested: initialization, termination, command
	\$2	Return code

**Action**            One or more messages will be written to the console to indicate the nature of the error. Correct these problems and restart the server.

**References**        Not applicable

**HTP0030      HTTP header '\$1' unrecognized**

**Explanation**    A header was detected in an HTTP request that was not recognized by the HTTP server. The header is ignored and the request is processed normally, ignoring the specified header.

<b>Placeholders</b>	\$1	Name of the header found in the HTTP request that was not recognized by the HTTP server.
---------------------	-----	--

**Action**            Report this to your technical support representative. While this is not an error as such, it is possible that the HTTP header should be recognized in a future release of the HTTP server.

**References**        Not applicable

**HTP0031      Unsupported request data \$1/x\$2**

**Explanation**    In the unformatted portion of an HTTP request, the HTTP server expects data as specified in the HTTP V1/1 protocol standard. If more information than normal is provided, or if the HTTP server makes an error interpreting the request, this message is issued. The request is processed normally; however, the data indicated in the message placeholders is be taken into account in the processing of the request.

<b>Placeholders</b>	\$1	The data provided on the request that the HTTP server ignored in character format.
	\$2	The data provided on the request that the HTTP server ignored in hexadecimal format.

**Action**            Report this to your technical support representative. While this is not an error as such, it is possible that the HTTP request data should be recognized in a future release of the HTTP server.

**References**        Not applicable

**HTP0032 Header '\$1' data '\$2' ignored**

**Explanation** The HTTP server recognized the header identified by the \$1 placeholder, however, it had to ignore the data as identified by the \$2 placeholder. This generally occurs due to a shortage of working space in the HTTP server request processing areas. The request is processed, however, the ignored header data, as shown in this message, is not taken into account while processing the request.

**Placeholders**

\$1	Name of the HTTP header for which the data was ignored.
\$2	The data (or at least the start of the data) that was ignored for the header identified by \$1.

**Action** Report this to your technical support representative. While this is not an error as such, it indicates that certain values within the HTTP server request interpretation processing may need to be reviewed.

**References** Not applicable

**HTP0033 Environment interface \$1 request failed rc=\$2**

**Explanation** A call to the environment dependent interface failed. Environmental components are called for initialization, termination and for initialization of the listening task.

**Placeholders**

\$1	The server function requested: ENVINIT, ENVTERM, or LISTINIT
\$2	Return code

**Action** Report the error to your local support center.

**References** Not applicable

**HTP0034      \$1 Invalid data \$2/x\$3 for program**

**Explanation** One of the HTTP server thread processing programs HAANLIST or HAANRQST is started by a mechanism apart from the internal processing of the HTTP server. These programs expect specific parameters that can only be provided via the internal HTTP server mechanisms.

<b>Placeholders</b>	\$1	Name of the program that was started with the invalid data.
	\$2	The invalid data provided to the program in character format.
	\$3	The invalid data provided to the program in hexadecimal format.

**Action** Determine who or what is attempting to start these programs in an incorrect way and force them to stop.

**References** Not applicable

**HTP0035      SMARTS API \$1 Request failed rc=\$2/errno=\$3**

**Explanation** An error occurred for a request made to the SMARTS environment.

<b>Placeholders</b>	\$1	Name of the request.
	\$2	Return code.
	\$3	Error number.

**Action** Refer to the SMARTS SDK Programmer's Reference Manual to determine why the errno was returned for the request and correct the error. Note that in many cases, these "errors" may be normal due to general activity on the TCP/IP network, for example.

**References** SMARTS SDK Programmer's Guide

**HTP0036      Server waiting for \$1 user(s) to terminate**

**Explanation** The server cannot terminate correctly until all users have terminated. The message indicates the number of users upon which the server is waiting.

<b>Placeholders</b>	\$1	The number of users still active.
---------------------	-----	-----------------------------------

**Action** Wait until all users have terminated and reissue the request to QUIESCE or TERMINATE the server. The server may be forced; however, this is not recommended due to the subsequent problems it can cause.

**References** Not applicable

**HTP0037      Operator command \$1 issued successfully**

**Explanation**    The operator command identified in the message has been successfully issued to the server.

<b>Placeholders</b>	<table><tr><td data-bbox="391 338 479 390">\$1</td><td data-bbox="479 338 1383 390">Name of the operator command issued.</td></tr></table>	\$1	Name of the operator command issued.
\$1	Name of the operator command issued.		

**Action**            This is an informational message: no action is necessary.

**References**       Not applicable

**HTP0039      HTTP server \$1 active on port \$2**

**Explanation**    The HTTP listening task attached for the server indicated by the \$1 placeholder has been started successfully and is now listening for incoming HTTP requests on the TCP/IP port identified by the \$2 placeholder.

<b>Placeholders</b>	\$1	Name of the HTTP server as specified on the SMARTS server environment SERVER configuration parameter or operator command.
	\$2	The TCP/IP port number on which the HTTP server is listening. This is set using the HTTP server configuration parameter PORT.

**Action**            Not applicable

**References**       The HTTP Server installation ionformation.



**HTP0040      Module not found \$1**

**Explanation**      The module identified by the \$1 placeholder cannot be found. A request to the operating system to load the module has failed. Modules to be loaded by the HTTP server must be available either in

- the COMPLIB DD concatenation or system LNKLIST for OS/390 and MSP systems; or
- a library identified in the search path for VSE.

If this message is issued during the initialization process, initialization fails if the module is required for the correct operation of the HTTP server. Otherwise, initialization continues.

If this message is issued during the termination process, termination continues; however, depending on the function of the module, the termination process may not complete successfully.

**Placeholders**

\$1	Name of the module that could not be found
-----	--

**Action**      If the module should be available during initialization and/or termination processing, determine why it cannot be found.

**References**      Not applicable

**HTP0041      Module \$1 load error rc=\$2/\$3**

**Explanation**    The module identified by the \$1 placeholder could not be loaded due to an error during LOAD processing. A request to the operating system to load the module failed for some reason other than the fact that the module could not be found.

If this message is issued during the initialization process, initialization fails if the module is required for the correct operation of the HTTP server. Otherwise, initialization continues.

If this message is issued during the termination process, termination continues; however, depending on the function of the module, the termination process may not complete successfully.

**Placeholders**

\$1	Name of the module for which the LOAD request failed.
\$2	Return code from the operating system LOAD request.
\$3	Reason code from the operating system LOAD request.

**Action**            Determine from the return and reason codes why the LOAD request failed and correct the error.

**References**

- *MVS/ESA Assembler Programmers Macro Reference Manual*
- *VSE/ESA Assembler Programmers Macro Reference Manual*

**HTP0042      Module \$1 issued return code \$2**

**Explanation**    A number of modules are called internally during HTTP server initialization and termination. These modules generally issue a 0 return code when they complete successfully. This message is issued when a module is called and its return code is not 0. When a non-zero return code is issued, the module responsible issues a message itself to indicate where the problem lies.

Initialization processing continues if the return code is less than 8 and terminates if the return code is 8 or greater.

Termination processing continues; however, if the return code is 8 or greater, there may be additional failures later in the termination process.

**Placeholders**

\$1	Name of the module that issued the return code
\$2	Return code issued by the module identified by \$1.

**Action**            Refer to preceding messages in the log to determine why the return code was issued. Correct the situation.

**References**      Not applicable

**HTP0043      Server \$1 initialization successful**

**Explanation**      Initialization processing for the HTTP server identified by the \$1 placeholder completed successfully.

<b>Placeholders</b>	\$1	Name of the HTTP server as specified on the SMARTS server environment SERVER configuration parameter or operator command.

**Action**              Not applicable

**References**        Not applicable

**HTP0044      Server \$1 terminating on port \$2**

**Explanation**      The HTTP server as identified in the \$1 placeholder is no longer listening for incoming HTTP requests on the port specified by placeholder \$2. This generally indicates that an error has occurred on the sockets 'listen' or 'accept' request, which in turn indicates that the TCP/IP connection has problems.

<b>Placeholders</b>	\$1	Name of the HTTP server as specified on the SMARTS server environment SERVER configuration parameter or operator command.
	\$2	The TCP/IP port number on which the HTTP server was listening.

**Action**              Not applicable

**References**        SMARTS Installation and Operations Manual

**HTP0047      Server \$1 terminated**

**Explanation**      The HTTP server identified by the \$1 placeholder terminated successfully.

<b>Placeholders</b>	\$1	Name of the HTTP server as specified on the SMARTS server environment SERVER configuration parameter or operator command.

**Action**              Not applicable

**References**        Not applicable

**HTP0048      Unrecognized operator command \$1**

**Explanation** An operator command was issued to the HTTP server using the SMARTS server environment SERVER operator command; however, the operator command was not processed because it was not recognized by the HTTP server.

<b>Placeholders</b>	<table border="1"> <tr> <td data-bbox="389 373 438 495">\$1</td><td data-bbox="438 373 1380 495">The operator command provided on the SMARTS server environment SERVER operator command for the HTTP server that was not recognized by the HTTP server.</td></tr> </table>	\$1	The operator command provided on the SMARTS server environment SERVER operator command for the HTTP server that was not recognized by the HTTP server.
\$1	The operator command provided on the SMARTS server environment SERVER operator command for the HTTP server that was not recognized by the HTTP server.		

**Action** Issue a valid operator command.

**References** The chapter HTTP Server Use and Customization starting on page in this manual.

**HTP0054      Server \$1 using \$2 configuration**

**Explanation** The HTTP server identified by the \$1 placeholder is initializing with the HTTP server configuration parameters specified by the \$2 placeholder.

Placeholders	\$1	Name of the HTTP server as specified on the SMARTS server environment SERVER configuration parameter or operator command.
	\$2	Name of the HTTP server configuration parameter module that will be used by this instance of the HTTP server for its configuration information.

**Action** Not applicable

**References** The chapter HTTP Server Use and Customization starting on page in this manual.

**HTP0055      Invalid configuration file \$1 data=\$2/x\$3**

**Explanation** The HTTP server configuration file identified by the \$1 placeholder starts with invalid data and thus cannot be used by the HTTP server for its configuration processing. The HTTP server initialization process terminates.

Placeholders	\$1	Name of the configuration file found to be invalid.
	\$2	The data found at the start of the invalid module in character format.
	\$3	The data found at the start of the invalid module in hexadecimal format.

- Ensure that the module was generated using the procedures and samples provided with SMARTS.
- Ensure that another module of the same name is not higher in the COMPLIB concatenation or VSE search path than the HTTP configuration module you wish to use.

**References** The information on installation, as well as customization and use of the HTTP Server.

**HTP0056      Server cannot initialize - SMARTS environment not active**

**Explanation**    The SMARTS environment must be active before the HTTP server can be activated. During its initialization processing, the HTTP server determined that the SMARTS environment was not active.

**Placeholders**   Not applicable

**Action**

- If the HTTP server is being started with the SMARTS environment SERVER configuration parameter, ensure that it appears before the HTTP SERVER statement(s) in the SMARTS environment configuration file.
- If the HTTP server is being started with the SMARTS environment SERVER operator command, start the SMARTS environment first.

**References**    *SMARTS Installation and Operations Manual*

**HTP0057      Module '\$1' attach failed rc=\$2**

**Explanation**    The HTTP server uses internal SMARTS server environment functions to start new processes in the SMARTS region. An attempt to attach the program identified by the \$1 placeholder failed.

If this program is HAANLIST, no task was available to listen on the appropriate port for a given instance of the HTTP server.

If the module name is HAANRQST (or an alternate name assigned by the user), that particular request itself fails; however, the HTTP server remains active and listening

**Placeholders**

\$1	Name of the program for which the attach request failed
\$2	Return code from the SMARTS server environment request issued as follows:

4	Insufficient TIBs available in the system
8	Program to be attached was not found
12	Security error
16	Invalid program name to be attached
20	Insufficient space in the SMARTS server environment general buffer pool

RC	Action
4	The number of TIBs available in the system is determined by the SMARTS server environment configuration parameter TIBTAB. Review the parameter setting based on the appropriate section in the <i>SMARTS Installation and Operations Manual</i> .
8	The program cannot be found if the HTTP server configuration parameter HTTPRQST specifies a program name that is not available to the SMARTS system.
8, 16	Report these errors to your technical support representative.

**Action**

RC	Action
4	The number of TIBs available in the system is determined by the SMARTS server environment configuration parameter TIBTAB. Review the parameter setting based on the appropriate section in the <i>SMARTS Installation and Operations Manual</i> .
8	The program cannot be found if the HTTP server configuration parameter HTTPRQST specifies a program name that is not available to the SMARTS system.
8, 16	Report these errors to your technical support representative.

**References**

- *SMARTS Installation and Operations Manual*
- *Complete System Programmer's Manual*